

```
*****
* Gasperini P. and Vannucci G., FPSPACK: a package of simple Fortran
subroutines
* to manage earthquake focal mechanism data
*
*****
*      BASIC ROUTINES
*****
*****
```

subroutine pl2nd(strike,dip,rake,anx,any,anz,dx,dy,dz,ierr)

C
C compute Cartesian components of outward normal and slip
C vectors from strike, dip and rake
C
C usage:
C call pl2nd(strike,dip,rake,anx,any,anz,dx,dy,dz,ierr)
C
C arguments:
C strike strike angle in degrees (INPUT)
C dip dip angle in degrees (INPUT)
C rake rake angle in degrees (INPUT)
C anx,any,anz components of fault plane outward normal verson in
the
C Aki-Richards Cartesian coordinate system (OUTPUT)
C dx,dy,dz components of slip verson in the Aki-Richards
C Cartesian coordinate system (OUTPUT)
C ierr error indicator (OUTPUT)
C
C errors:
C 1 input STRIKE angle out of range
C 2 input DIP angle out of range
C 4 input RAKE angle out of range
C 3 1+2
C 5 1+4
C 7 1+2+4
C
C implicit none

integer io
real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io

real anx,any,anz,dx,dy,dz,strike,dip,rake,wstrik,wdip,wrake
integer ierr

C
call fpsset
C
anx=c0
any=c0
anz=c0
dx=c0
dy=c0

```

dz=c0
ierr=0
if(strike.lt.amistr.or.strike.gt.amastr) then
    write(io,'(1x,a,g10.4,a)') 'PL2ND: input STRIKE angle ',strike,
1  ' out of range'
    ierr=1
endif
if(dip.lt.amidip.or.dip.gt.amadip) then
    if(dip.lt.amadip.and.dip.gt.-ovrtol) then
        dip=amidip
    else if(dip.gt.amidip.and.dip-amadip.lt.ovrtol) then
        dip=amadip
    else
        write(io,'(1x,a,g10.4,a)') 'PL2ND: input DIP angle ',dip,
1      ' out of range'
        ierr=ierr+2
    endif
endif
if(rake.lt.amirak.or.rake.gt.amarak) then
    write(io,'(1x,a,g10.4,a)') 'PL2ND: input RAKE angle ',rake,
1  ' out of range'
    ierr=ierr+4
endif
if(ierr.ne.0) return
wstrik=strike*dtor
wdip=dip*dtor
wrake=rake*dtor
C
anx=-sin(wdip)*sin(wstrik)
any=sin(wdip)*cos(wstrik)
anz=-cos(wdip)
dx=cos(wrake)*cos(wstrik)+cos(wdip)*sin(wrake)*sin(wstrik)
dy=cos(wrake)*sin(wstrik)-cos(wdip)*sin(wrake)*cos(wstrik)
dz=-sin(wdip)*sin(wrake)
return
end
*****
***** subroutine nd2pl(wanx,wany,wanz,wdx,wdy,wdz,phi,delta,alam,dipdir
1,ierr)
C
C compute strike, dip, rake and dip directions from Cartesian
C components of the outward normal and slip vectors
C
C usage:
C call nd2pl(anx,any,anz,dx,dy,dz,strike,dip,rake,dipdir,ierr)
C
C arguments:
C anz,any,anz components of fault plane outward normal vector in
the
C Aki-Richards Cartesian coordinate system (INPUT)
C dx,dy,dz components of slip vector in the Aki-Richards
C Cartesian coordinate system (INPUT)
C strike strike angle in degrees (OUTPUT)
C dip dip angle in degrees (OUTPUT)
C rake rake angle in degrees (OUTPUT)
C dipdir dip direction angle in degrees (OUTPUT)
C ierr error indicator (OUTPUT)
C
C errors:

```

```

c      1           input vectors not perpendicular among each other
c
c      implicit none
c-----
----- integer io
      real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
----- real wanx,wany,wanz,wdx,wdy,wdz,ang,anorm,anx,any,anz,dnorm
1,dx,dy,dz,wdelta,wphi,walam,phi,delta,alam,dipdir
      integer ierr
c
      call fpsset
c
      ierr=0
      call angle(wanx,wany,wanz,wdx,wdy,wdz,ang)
      if(abs(ang-c90).gt.orttol) then
          write(io,'(1x,a,g15.7,a)') 'ND2PL: input vectors not '
1 //perpendicular, angle=',ang
          ierr=1
      endif
      call norm(wanx,wany,wanz,anorm,anx,any,anz)
      call norm(wdx,wdy,wdz,dnorm,dx,dy,dz)
      if(anz.gt.c0) then
          call invert(anx,any,anz)
          call invert(dx,dy,dz)
      endif
c
      if(anz.eq.-c1) then
          wdelta=c0
          wphi=c0
          walam=atan2(-dy,dx)
      else
          wdelta=acos(-anz)
          wphi=atan2(-anx,any)
          walam=atan2(-dz/sin(wdelta),dx*cos(wphi)+dy*sin(wphi))
      endif
      phi=wphi/dtor
      delta=wdelta/dtor
      alam=walam/dtor
      phi=mod(phi+c360,c360)
      dipdir=phi+c90
      dipdir=mod(dipdir+c360,c360)
      return
      end
*****
***** subroutine ax2ca(trend,plunge,ax,ay,az,ierr)
c
c      compute cartesian components from trend and plunge
c
c      usage:
c      call ax2ca(trend,plunge,ax,ay,az,ierr)
c
c      arguments:

```

```

c      trend           clockwise angle from North in degrees (INPUT)
c      plunge          inclination angle in degrees (INPUT)
c      ax,ay,az        components of the axis direction downward verson in
the
c                               Aki-Richards Cartesian coordinate system (OUTPUT)
c      ierr            error indicator (OUTPUT)
c
c      errors:
c      1               input TREND angle out of range
c      2               input PLUNGE angle out of range
c      3               1+2
c
c      implicit none
c-----
-----  

integer io
real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
-----  

real ax,ay,az,trend,plunge
integer ierr
c
call fpsset
c
ax=c0
ay=c0
az=c0
ierr=0
if(trend.lt.amitre.or.trend.gt.amatre) then
    write(io,'(1x,a,g10.4,a)') 'AX2CA: input TREND angle ',trend,
1  ' out of range'
    ierr=1
endif
if(plunge.lt.amiplu.or.plunge.gt.amaplu) then
    if(plunge.lt.amaplu.and.plunge.gt.-ovrtol) then
        plunge=amiplu
    else if(plunge.gt.amiplu.and.plunge-amaplu.lt.ovrtol) then
        plunge=amaplu
    else
        write(io,'(1x,a,g10.4,a)') 'AX2CA: input PLUNGE angle ',
1      plunge,' out of range'
        ierr=ierr+2
    endif
endif
if(ierr.ne.0) return
ax=cos(plunge*dtor)*cos(trend*dtor)
ay=cos(plunge*dtor)*sin(trend*dtor)
az=sin(plunge*dtor)
return
end
*****
*****  

subroutine ca2ax(wax,way,waz,trend,plunge,ierr)
c
c      compute trend and plunge from Cartesian components
c

```

```

c      usage:
c      call ca2ax(ax,ay,az,trend,plunge,ierr)
c
c      arguments:
c      ax,ay,az      components of axis direction vector in the Aki-
Richards
c                      Cartesian coordinate system (INPUT)
c      trend         clockwise angle from North in degrees (OUTPUT)
c      plunge        inclination angle in degrees (OUTPUT)
c      ierr          error indicator (OUTPUT)
c
c      errors:
c
c      implicit none
c-----
-----  

      integer io
      real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
      1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
      1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
      2,c3,io
c-----
-----  

      real wax,way,waz,wnorm,ax,ay,az,trend,plunge
      integer ierr
c
      call fpsset
c
      ierr=0
      call norm(wax,way,waz,wnorm,ax,ay,az)
      if(az.lt.c0) call invert(ax,ay,az)
      if(ay.ne.c0.or.ax.ne.c0) then
          trend=atan2(ay,ax)/dtor
      else
          trend=c0
      endif
      trend=mod(trend+c360,c360)
      plunge=asin(az)/dtor
      return
      end
*****
*****  

      subroutine pt2nd(wpx,wpy,wpz,wtx,wtty,wtz,anx,any,anz,dx,dy,dz
      1,ierr)
c
c      compute Cartesian component of P and T versors
c      from outward normal and slip vectors
c
c      usage:
c      call pt2nd(px,py,pz,tx,ty,tz,anx,any,anz,dx,dy,dz,ierr)
c
c      arguments:
c      px,py,pz      components of P (maximum dilatation) axis vector
c                      in the Aki-Richards Cartesian coordinate system
c (INPUT)
c      tx,ty,tz      components of T (maximum tension) axis vector
c                      in the Aki-Richards Cartesian coordinate system
c (INPUT)

```

```

c      anx,any,anz      components of fault plane outward normal verson in
the
c      dx,dy,dz          Aki-Richards Cartesian coordinate system (OUTPUT)
c      components of slip verson in the Aki-Richards
c      Cartesian coordinate system (OUTPUT)
c      ierr               error indicator (OUTPUT)
c
c      errors:
c      1                  input vectors not perpendicular among each other
c
c      implicit none
c-----
-----  

integer io
real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
-----  

real anx,any,anz,dx,dy,dz,wpx,wpy,wpz,wtx,wtz,ang,pnorm
1,px,py,pz,tnorm,tx,ty,tz,amn
integer ierr
c
call fpsset
c
anx=c0
any=c0
anz=c0
dx=c0
dy=c0
dz=c0
ierr=0
call angle(wpx,wpy,wpz,wtx,wtz,ang)
if(abs(ang-c90).gt.orttol) then
    write(io,'(1x,a,g15.7,a)') 'PT2ND: input vectors not '
1  //perpendicular, angle=',ang
    ierr=1
endif
call norm(wpx,wpy,wpz,pnorm,px,py,pz)
if(pz.lt.c0) call invert(px,py,pz)
call norm(wtx,wtz,wtz,tnorm,tx,ty,tz)
if(tz.lt.c0) call invert(tx,ty,tz)
anx=tx+px
any=ty+py
anz=tz+pz
call norm(anx,any,anz,amn,anx,any,anz)
c
dx=tx-px
dy=ty-py
dz=tz-pz
call norm(dx,dy,dz,amn,dx,dy,dz)
if(anz.gt.c0) then
    call invert(anx,any,anz)
    call invert(dx,dy,dz)
endif
return
end

```

```
*****
***** subroutine nd2pt(wanx,wany,wanz,wdx,wdy,wdz,px,py,pz,tx,ty,tz,bx
1,by,bz,ierr)
C
C      compute Cartesian component of P, T and B axes from outward normal
C      and slip vectors
C
C      usage:
C      call nd2pt(anx,any,anz,dx,dy,dz,px,py,pz,tx,ty,tz,bx,by,bz,ierr)
C
C      arguments:
C      anx,any,anz      components of fault plane outward normal vector in
the
C                      Aki-Richards Cartesian coordinate system (INPUT)
C      dx,dy,dz        components of slip vector in the Aki-Richards
C                      Cartesian coordinate system (INPUT)
C      px,py,pz        components of downward P (maximum dilatation) axis
vessor
C                      in the Aki-Richards Cartesian coordinate system
(OUPUT)
C      tx,ty,tz        components of downward T (maximum tension) axis
vessor
C                      in the Aki-Richards Cartesian coordinate system
(OUPUT)
C      bx,by,bz        components of downward B (neutral) axis vessor in
the
C                      Aki-Richards Cartesian coordinate system (OUTPUT)
C      ierr             error indicator (OUTPUT)
C
C      errors:
C      1                input vectors not perpendicular among each other
C
C      implicit none
C-----
-----
      integer io
      real amistr,amastr,midip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,midip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
C-----
-----
      real wanx,wany,wanz,amn,anx,any,anz,wdx,wdy,wdz,amd,dx,dy,dz
1,ang,px,py,pz,tx,ty,tz,bx,by,bz,amp
      integer ierr
C
      call fpsset
C
      ierr=0
      call norm(wanx,wany,wanz,amn,anx,any,anz)
      call norm(wdx,wdy,wdz,amd,dx,dy,dz)
      call angle(anx,any,anz,dx,dy,dz,ang)
      if(abs(ang-c90).gt.orttol) then
          write(io,'(1x,a,g15.7,a)') 'ND2PT: input vectors not '
1     //perpendicular, angle=',ang
          ierr=1
      endif
      px=anx-dx
```

```

py=any-dy
pz=anz-dz
call norm(px,py,pz,amp,px,py,pz)
if(pz.lt.c0) call invert(px,py,pz)
tx=anx+dx
ty=any+dy
tz=anz+dz
call norm(tx,ty,tz,amp,tx,ty,tz)
if(tz.lt.c0) call invert(tx,ty,tz)
call vecpro(px,py,pz,tx,ty,tz,bx,by,bz)
if(bz.lt.c0) call invert(bx,by,bz)
return
end
*****
***** subroutine ar2pt(am,am0,aml,e,am0b,px,py,pz,tx,ty,tz,bx,by,bz
1,eta,ierr)
c
c      compute Cartesian components of deformation axes (P, T and B)
c      from moment tensor (Aki & Richards convention)
c
c      usage:
c      call ar2pt(am,am0,aml,e,am0b,px,py,pz,tx,ty,tz,bx,by,bz,eta,ierr)
c
c      arguments:
c      am          seismic moment tensor (3x3 matrix) (INPUT)
c      am0         scalar seismic moment of principal double couple
c                  (OUTPUT)
c      aml         scalar seismic moment of secondary double couple
c                  (OUTPUT)
c      e           isotropic component (trace of the input tensor)
c                  (OUTPUT)
c      am0b        scalar seismic moment of best double couple (OUTPUT)
c      px,py,pz   components of downward P (maximum dilatation) axis
versor
c                           in the Aki-Richards Cartesian coordinate system
(OBJECT)
c      tx,ty,tz    components of downward T (maximum tension) axis
versor
c                           in the Aki-Richards Cartesian coordinate system
(OBJECT)
c      bx,by,bz    components of downward B (neutral) axis versor in
the
c                           Aki-Richards Cartesian coordinate system (OUTPUT)
c      eta         percentage of CLVD remainder (OUTPUT)
c      ierr        error indicator (OUTPUT)
c
c      errors:
c      1           input tensor not symmetrical: am(1,2).ne.am(2,1)
c      2           input tensor not symmetrical: am(1,3).ne.am(3,1)
c      3           input tensor not symmetrical: am(2,3).ne.am(3,2)
c
c      implicit none
c-----
----- integer io
real amistr,amastr,midip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
common /fpscom/amistr,amastr,midip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2

```

```

2,c3,io
c-----
-----
      real am,val,vec,am0,am1,e,px,py,pz,tx,ty,tz,bx,by,bz,am0b,eta,dum
      integer ierr,i,j,k
      dimension am(3,3),val(3),vec(3,3)
c
      call fpsset
c
      am0=c0
      am1=c0
      e=c0
      am0b=c0
      px=c0
      py=c0
      pz=c0
      tx=c0
      ty=c0
      tz=c0
      bx=c0
      by=c0
      bz=c0
      ierr=0
      if(abs(am(1,2)-am(2,1)).gt.tentol) then
          write(io,'(1x,a,g10.4,a,g10.4)') 'AR2PT: input tensor not'
1      // symmetrical, m(1,2)=' ,am(1,2), ' m(2,1)=' ,am(2,1)
          ierr=1
      endif
      if(abs(am(1,3)-am(3,1)).gt.tentol) then
          write(io,'(1x,a,g10.4,a,g10.4)') 'AR2PT: input tensor not'
1      // symmetrical, m(1,3)=' ,am(1,3), ' m(3,1)=' ,am(3,1)
          ierr=ierr+2
      endif
      if(abs(am(3,2)-am(2,3)).gt.tentol) then
          write(io,'(1x,a,g10.4,a,g10.4)') 'AR2PT: input tensor not'
1      // symmetrical, m(2,3)=' ,am(2,3), ' m(3,2)=' ,am(3,2)
          ierr=ierr+4
      endif
      if(ierr.ne.0) return
      call avec(am,val,vec)
      e=(val(1)+val(2)+val(3))/c3
c
c      compute deviatoric eigenvalues
c
      do i=1,3
          val(i)=val(i)-e
      enddo
c
c      sort deviatoric eigenvalues (with isotropic component removed)
c      and eigenvectors by inverse order of eigenvalue modulus magnitude
c
1      do 2 i=1,2
          do 3 j=i+1,3
              if(abs(val(i)).lt.abs(val(j))) then
                  dum=val(i)
                  val(i)=val(j)
                  val(j)=dum
                  do 4 k=1,3
                      dum=vec(k,i)
                      vec(k,i)=vec(k,j)

```

```

        vec(k,j)=dum
4      continue
      endif
3      continue
2      continue
am0=val(1)
eta=-val(3)/(c2*am0)
aml=abs(val(3))
am0b=(abs(val(1))+abs(val(2)))/c2
if(am0.lt.c0) then
  am0=-am0
  tx=vec(1,2)
  ty=vec(2,2)
  tz=vec(3,2)
  px=vec(1,1)
  py=vec(2,1)
  pz=vec(3,1)
  bx=vec(1,3)
  by=vec(2,3)
  bz=vec(3,3)
else
  tx=vec(1,1)
  ty=vec(2,1)
  tz=vec(3,1)
  px=vec(1,2)
  py=vec(2,2)
  pz=vec(3,2)
  bx=vec(1,3)
  by=vec(2,3)
  bz=vec(3,3)
endif
return
end
*****
***** subroutine nd2ar(anx,any,anz,dx,dy,dz,am0,am,ierr)
C
C      compute moment tensor Cartesian components (Aki & Richards
convention)
C      from outward normal and slip vectors Cartesian components
C
C      usage:
C      call nd2ar(anx,any,anz,dx,dy,dz,am0,am,ierr)
C
C      arguments:
C      anx,any,anz      components of fault plane outward normal vector in
the
C                      Aki-Richards Cartesian coordinate system (INPUT)
C      dx,dy,dz       components of slip vector in the Aki-Richards
Cartesian coordinate system (INPUT)
C      am0            scalar seismic moment (INPPUT)
C      am             seismic moment tensor (3x3 matrix) (OUTPUT)
C      ierr           error indicator (OUTPUT)
C
C      errors:
C      1              input vectors not perpendicular among each other
C
C      implicit none
C-----
-----
```

```

integer io
real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
-----
      real anx,any,anz,dx,dy,dz,am0,am,aam0,ang,anorm,wanx,wany,wanz
1,wdx,wdy,wdz
      integer ierr,i,j
      dimension am(3,3)
c
      call fpsset
c
      do 1 i=1,3
         do 2 j=1,3
            am(i,j)=c0
2      continue
1      continue
      if(am0.eq.c0) then
         aam0=c1
      else
         aam0=am0
      endif
      ierr=0
      call angle(anx,any,anz,dx,dy,dz,ang)
      if(abs(ang-c90).gt.orttol) then
         write(io,'(1x,a,g15.7,a)') 'ND2AR: input vectors not '
1         // 'perpendicular, angle=',ang
         ierr=1
      endif
      call norm(anx,any,anz,anorm,wanx,wany,wanz)
      call norm(dx,dy,dz,anorm,wdx,wdy,wdz)
      am(1,1)=aam0*c2*wdx*wanx
      am(1,2)=aam0*(wdx*wany+wdy*wanx)
      am(2,1)=am(1,2)
      am(1,3)=aam0*(wdx*wanz+wdz*wanx)
      am(3,1)=am(1,3)
      am(2,2)=aam0*c2*wdy*wany
      am(2,3)=aam0*(wdy*wanz+wdz*wany)
      am(3,2)=am(2,3)
      am(3,3)=aam0*c2*wdz*wanz
      return
      end
*****
***** subroutine ar2ha(am,amo(ierr)
c
c      transforms moment tensor component from Aki Richards to Harvard CMT
c      reference systems and viceversa
c
c      usage:
c      call ar2ha(am,amo(ierr)
c
c      arguments:
c      am           input seismic moment tensor (3x3 matrix) (INPUT)
c      amo          output seismic moment tensor (3x3 matrix) (OUTPUT)
c      ierr         error indicator (OUTPUT)
c

```

```

c      errors:
c      1           input tensor not symmetrical: am(1,2).ne.am(2,1)
c      2           input tensor not symmetrical: am(1,3).ne.am(3,1)
c      3           input tensor not symmetrical: am(2,3).ne.am(3,2)
c
c      implicit none
c-----
----- integer io
      real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
----- real am,amo
      integer ierr,i,j
      dimension am(3,3),amo(3,3)
c
      call fpsset
c
      ierr=0
      if(abs(am(1,2)-am(2,1)).gt.tentol) then
          write(io,'(1x,a,g10.4,a,g10.4)') 'AR2HA: input tensor not'
1 //' symmetrical, m(1,2)=' ,am(1,2), ' m(2,1)=' ,am(2,1)
          ierr=1
      endif
      if(abs(am(1,3)-am(3,1)).gt.tentol) then
          write(io,'(1x,a,g10.4,a,g10.4)') 'AR2HA: input tensor not'
1 //' symmetrical, m(1,3)=' ,am(1,3), ' m(3,1)=' ,am(3,1)
          ierr=ierr+2
      endif
      if(abs(am(3,2)-am(2,3)).gt.tentol) then
          write(io,'(1x,a,g10.4,a,g10.4)') 'AR2HA: input tensor not'
1 //' symmetrical, m(2,3)=' ,am(2,3), ' m(3,2)=' ,am(3,2)
          ierr=ierr+4
      endif
      if(ierr.ne.0) then
          do 1 i=1,3
              do 2 j=1,3
                  amo(i,j)=c0
2          continue
1          continue
          return
      endif
      amo(1,1)=am(1,1)
      amo(1,2)=-am(1,2)
      amo(1,3)=am(1,3)
      amo(2,1)=-am(2,1)
      amo(2,2)=am(2,2)
      amo(2,3)=-am(2,3)
      amo(3,1)=am(3,1)
      amo(3,2)=-am(3,2)
      amo(3,3)=am(3,3)
      return
  end
*****
***** *      COMPOSITE ROUTINES

```

```

*****
***** subroutine nd2ha(anx,any,anz,dx,dy,dz,am0,am,ierr)
c
c compute moment tensor Cartesian components (Harvard CMT convention)
c from outward normal and slip vectors Cartesian components
c
c usage:
c call nd2ha(anx,any,anz,dx,dy,dz,am0,am,ierr)
c
c arguments:
c anz,any,anz      components of fault plane outward normal vector in
the
c                               Aki-Richards Cartesian coordinate system (INPUT)
c dx,dy,dz        components of slip vector in the Aki-Richards
c                               Cartesian coordinate system (INPUT)
c am0             scalar seismic moment (INPPUT)
c am              seismic moment tensor (3x3 matrix) (OUTPUT)
c ierr            error indicator (OUTPUT)
c
c errors:
c 1               input vectors not perpendicular among each other
c 2               internal error
c
c implicit none
c-----
----- integer io
real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
----- real am,anx,any,anz,dx,dy,dz,am0
integer ierr,i,j
dimension am(3,3)
c
call fpsset
c
do 1 i=1,3
   do 2 j=1,3
      am(i,j)=c0
2      continue
1      continue
ierr=0
call nd2ar(anx,any,anz,dx,dy,dz,am0,am,ierr)
if(ierr.ne.0) then
   write(io,'(1x,a,i3)') 'ND2HA: ierr=',ierr
   return
endif
call ar2ha(am,am,ierr)
if(ierr.ne.0) then
   ierr=2
   write(io,'(1x,a,i3)') 'ND2HA: ierr=',ierr
endif
return
end
```

```

*****
***** subroutine pl2pl(strika,dipa,rakea,strikb,dipb,rakeb,
1dipdib,ierr)
C
C      compute strike, dip and rake of a nodal plane
C      from strike, dip and rake of the other one
C
C
C      usage:
C      call pl2pl(strika,dipa,rakea,strikb,dipb,rakeb,dipdib,ierr)
C
C      arguments:
C      strika          strike angle in degrees of the first nodal plane
C (INPUT)
C      dipa            dip angle in degrees of the first nodal plane
C (INPUT)
C      rakea           rake angle in degrees of the first nodal plane
C (INPUT)
C      strikb          strike angle in degrees of the second nodal plane
C (OUTPUT)
C      dipb            dip angle in degrees of the second nodal plane
C (OUTPUT)
C      rakeb           rake angle in degrees of the second nodal plane
C (OUTPUT)
C      dipdib          dip direction in degrees of the second nodal plane
C (OUTPUT)
C      ierr             error indicator (OUTPUT)
C
C      errors:
C      1                input STRIKE angle out of range
C      2                input DIP angle out of range
C      4                input RAKE angle out of range
C      3                1+2
C      5                1+4
C      7                1+2+4
C      8                internal error
C
C      implicit none
C-----
----- integer io
real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
C-----
----- real strika,dipa,rakea,anx,any,anz,dx,dy,dz,strikb,dipb,rakeb,
1dipdib
integer ierr
C
call fpsset
C
call pl2nd(strika,dipa,rakea,anx,any,anz,dx,dy,dz,ierr)
if(ierr.ne.0) then
    write(io,'(1x,a,i3)') 'PL2PL: ierr=',ierr
    return
endif

```

```

call nd2pl(dx,dy,dz,anx,any,anz,strikb,dipb,rakeb,dipdib,ierr)
if(ierr.ne.0) then
  ierr=8
  write(io,'(1x,a,i3)') 'PL2PL: ierr=',ierr
endif
return
end
*****
***** subroutine pl2pt(strike,dip,rake,trendp,plungp,trendt,plungt,
1trendb,plungb,ierr)
c
c      compute trend and plunge of P, T and B axes
c      from strike, dip and rake of a nodal plane
c
c
c      usage:
c      call
pl2pt(strike,dip,rake,trendp,plungp,trendt,plungt,trendb,plungb,ierr)
c
c      arguments:
c      strike          strike angle in degrees of the first nodal plane
c      (INPUT)
c      dip             dip angle in degrees of the first nodal plane
c      (INPUT)
c      rake            rake angle in degrees of the first nodal plane
c      (INPUT)
c      trendp          trend of P axis (OUTPUT)
c      plungp          plunge or P axis (OUTPUT)
c      trendt          trend of T axis (OUTPUT)
c      plungt          plunge or T axis (OUTPUT)
c      trendb          trend of B axis (OUTPUT)
c      plungb          plunge or B axis (OUTPUT)
c      ierr            error indicator (OUTPUT)
c
c      errors:
c      1               input STRIKE angle out of range
c      2               input DIP angle out of range
c      4               input RAKE angle out of range
c      3               1+2
c      5               1+4
c      7               1+2+4
c      8,9,10,11       internal error
c
c      implicit none
c-----
-----
      integer io
      real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
-----
      real strike,dip,rake,anx,any,anz,dx,dy,dz,px,py,pz,tx,ty,tz
1,bx,by,bz,trendp,plungp,trendt,plungt,trendb,plungb
      integer ierr
c
      call fpsset

```

```

C
call pl2nd(strike,dip,rake,anx,any,anz,dx,dy,dz,ierr)
if(ierr.ne.0) then
    write(io,'(1x,a,i3)') 'PL2PT: ierr=',ierr
    return
endif
call nd2pt(dx,dy,dz,anx,any,anz,px,py,pz,tx,ty,tz,bx,by,bz,ierr)
if(ierr.ne.0) then
    ierr=8
    write(io,'(1x,a,i3)') 'PL2PT: ierr=',ierr
endif
call ca2ax(px,py,pz,trendp,plungp,ierr)
if(ierr.ne.0) then
    ierr=9
    write(io,'(1x,a,i3)') 'PL2PT: ierr=',ierr
endif
call ca2ax(tx,ty,tz,trendt,plungt,ierr)
if(ierr.ne.0) then
    ierr=10
    write(io,'(1x,a,i3)') 'PL2PT: ierr=',ierr
endif
call ca2ax(bx,by,bz,trendb,plungb,ierr)
if(ierr.ne.0) then
    ierr=11
    write(io,'(1x,a,i3)') 'PL2PT: ierr=',ierr
endif
return
end
*****
***** subroutine pt2pl(trendp,plungp,trendt,plungt,strika,dipa,rakea
1,dipdia,strikb,dipb,rakeb,dipdib,ierr)
C
C      compute strike dip and rake (and dip direction) of two nodal planes
C      from trend and plunge of P and T axes
C
C      usage:
C      call pt2pl(trendp,plungp,trendt,plungt,strika,dipa,rakea
C      1,dipdia,strikb,dipb,rakeb,dipdib,ierr)
C
C      arguments:
C      trendp          trend of P axis in degrees (INPUT)
C      plungp          plunge of P axis in degrees (INPUT)
C      trendt          trend of T axis in degrees (INPUT)
C      plungt          plunge of T axis in degrees (INPUT)
C      strika         strike angle of first nodal plane in degrees
C                      (OUTPUT)
C      dipa            dip angle of first nodal plane in degrees (OUTPUT)
C      rakea           rake angle of first nodal plane in degrees (OUTPUT)
C      dipdia          dip direction angle of first nodal plane in degrees
C                      (OUTPUT)
C      strikb          strike angle of second nodal plane in degrees
C                      (OUTPUT)
C      dipb            dip angle of second nodal plane in degrees (OUTPUT)
C      rakeb           rake angle of second nodal plane in degrees (OUTPUT)
C      dipdib          dip direction angle of second nodal plane in degrees
C                      (OUTPUT)
C      ierr            error indicator (OUTPUT)
C
C      errors:

```

```

c      1           input TREND angle of P axis out of range
c      2           input PLUNGE angle P axis out of range
c      3           1+2
c      4           input TREND angle of P axis out of range
c      5           input PLUNGE angle P axis out of range
c      6           4+5
c      8,9,10       internal errors
c
c      implicit none
c-----
----- integer io
real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
----- real trendp,plungp,trendt,plungt,px,py,pz,tx,ty,tz
1,anx,any,anz,dx,dy,dz,strika,dipa,rakea,dipdia,strikb,dipb
1,rakeb,dipdib
integer ierr
c
call fpsset
c
call ax2ca(trendp,plungp,px,py,pz,ierr)
if(ierr.ne.0) then
    write(io,'(1x,a,i3)') 'PT2PL: ierr=',ierr
    return
endif
call ax2ca(trendt,plungt,tx,ty,tz,ierr)
if(ierr.ne.0) then
    ierr=ierr+3
    write(io,'(1x,a,i3)') 'PT2PL: ierr=',ierr
    return
endif
call pt2nd(px,py,pz,tx,ty,tz,anx,any,anz,dx,dy,dz,ierr)
if(ierr.ne.0) then
    ierr=8
    write(io,'(1x,a,i3)') 'PT2PL: ierr=',ierr
    return
endif
call nd2pl(anx,any,anz,dx,dy,dz,strika,dipa,rakea,dipdia,ierr)
if(ierr.ne.0) then
    ierr=9
    write(io,'(1x,a,i3)') 'PT2PL: ierr=',ierr
    return
endif
call nd2pl(dx,dy,dz,anx,any,anz,strikb,dipb,rakeb,dipdib,ierr)
if(ierr.ne.0) then
    ierr=10
    write(io,'(1x,a,i3)') 'PT2PL: ierr=',ierr
    return
endif
return
end
c
*****
```

```

subroutine ar2plp(am,am0,am1,e,am0b,phia,deltaa,alama,slipa,
1phib,deltab,alamb,slipb,trendp,plungp,trendt,plungt,trendb,
2plungb,eta,ierr)
c
c      compute planes and axes of principal double couple
c      from moment tensor (Aki & Richards convention)
c
c      usage:
c      call ar2plp(am,am0,am1,e,am0b,phia,deltaa,alama,slipa,
c      1phib,deltab,alamb,slipb,trendp,plungp,trendt,plungt,trendb,
c      2plungb,eta,ierr)
c
c      arguments:
c      am          seismic moment tensor (3x3 matrix) (INPUT)
c      am0         scalar seismic moment of principal double couple
c                  (OUTPUT)
c      am1         scalar seismic moment of secondary double couple
c                  (OUTPUT)
c      e           isotropic component (trace of the input tensor)
c                  (OUTPUT)
c      am0b        scalar seismic moment of best double couple (OUTPUT)
c      phia        strike angle in degrees of the first nodal plane
c                  (OUTPUT)
c      deltaa      dip angle in degrees of the first nodal plane
c                  (OUTPUT)
c      alama      rake angle in degrees of the first nodal plane
c                  (OUTPUT)
c      slipa       dip direction in degrees of the first nodal plane
c                  (OUTPUT)
c      phib        strike angle in degrees of the second nodal plane
c                  (OUTPUT)
c      deltab      dip angle in degrees of the second nodal plane
c                  (OUTPUT)
c      alamb      rake angle in degrees of the second nodal plane
c                  (OUTPUT)
c      slipb       dip direction in degrees of the second nodal plane
c                  (OUTPUT)
c      trendp      trend angle in degrees of the P axis (OUTPUT)
c      plungp     plunge angle in degrees of the P axis (OUTPUT)
c      trendt      trend angle in degrees of the T axis (OUTPUT)
c      plungt     plunge angle in degrees of the T axis (OUTPUT)
c      trendb      trend angle in degrees of the B axis (OUTPUT)
c      plungb     plunge angle in degrees of the B axis (OUTPUT)
c      eta         percentage of CLVD remainder (OUTPUT)
c      ierr        error indicator (OUTPUT)
c
c      errors:
c      1           input tensor not symmetrical: am(1,2).ne.am(2,1)
c      2           input tensor not symmetrical: am(1,3).ne.am(3,1)
c      3           input tensor not symmetrical: am(2,3).ne.am(3,2)
c      5,6,7,8,9,10 internal errors
c
c      implicit none
c-----
-----  

      integer io
      real amistr,amastr,midip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,midip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2

```

```

2,c3,io
c-----
-----
      real am,am0,am1,e,am0b,phia,deltaa,alama,slipa,phib,deltab
1,alamb,slipb,trendp,plungp,trendt,plungt,trendb,plungb
2,px,py,pz,tx,ty,tz,anx,any,anz,dx,dy,dz,bx,by,bz,eta
      integer ierr
      dimension am(3,3)
c
      call fpsset
c
      am0=c0
      am1=c0
      e=c0
      am0b=c0
      phia=c0
      deltaa=c0
      alama=c0
      slipa=c0
      phib=c0
      deltab=c0
      alamb=c0
      slipb=c0
      trendp=c0
      plungp=c0
      trendt=c0
      plungt=c0
      trendb=c0
      plungb=c0
      ierr=0
      call ar2pt(am,am0,am1,e,am0b,px,py,pz,tx,ty,tz,bx,by,bz,eta,ierr)
      if(ierr.ne.0) then
          write(io,'(1x,a,i3)') 'AR2PLP: ierr=',ierr
          return
      endif
      call ca2ax(px,py,pz,trendp,plungp,ierr)
      if(ierr.ne.0) then
          ierr=5
          write(io,'(1x,a,i3)') 'AR2PLP: ierr=',ierr
          return
      endif
      call ca2ax(tx,ty,tz,trendt,plungt,ierr)
      if(ierr.ne.0) then
          ierr=6
          write(io,'(1x,a,i3)') 'AR2PLP: ierr=',ierr
          return
      endif
      call ca2ax(bx,by,bz,trendb,plungb,ierr)
      if(ierr.ne.0) then
          ierr=7
          write(io,'(1x,a,i3)') 'AR2PLP: ierr=',ierr
          return
      endif
      call pt2nd(px,py,pz,tx,ty,tz,anx,any,anz,dx,dy,dz,ierr)
      if(ierr.ne.0) then
          ierr=8
          write(io,'(1x,a,i3)') 'AR2PLP: ierr=',ierr
          return
      endif
      call nd2pl(anx,any,anz,dx,dy,dz,phia,deltaa,alama,slipa,ierr)

```

```

if(ierr.ne.0) then
  ierr=9
  write(io,'(1x,a,i3)') 'AR2PLP: ierr=',ierr
  return
endif
call nd2pl(dx,dy,dz,anx,anz,phib,deltab,alamb,slipb,ierr)
if(ierr.ne.0) then
  ierr=10
  write(io,'(1x,a,i3)') 'AR2PLP: ierr=',ierr
  return
endif
return
end
*****
***** subroutine ha2plp(am,am0,am1,e,am0b,strika,dipa,rakea,slipa,
1strikb,dipb,rakeb,slipb,trendp,plungp,trendt,plungt,trendb,
2plungb,eta,ierr)
c
c   compute planes and axes of principal double couple
c   from moment tensor (Harvard CMT convention)
c
c   usage:
c     subroutine ha2plp(am,am0,am1,e,am0b,strika,dipa,rakea,slipa,
c     1strikb,dipb,rakeb,slipb,trendp,plungp,trendt,plungt,trendb,
c     2plungb,eta,ierr)
c
c   arguments:
c     am          seismic moment tensor (3x3 matrix) (INPUT)
c     am0         scalar seismic moment of principal double couple
c                  (OUTPUT)
c     am1         scalar seismic moment of secondary double couple
c                  (OUTPUT)
c     e           isotropic component (trace of the input tensor)
c                  (OUTPUT)
c     am0b        scalar seismic moment of best double couple (OUTPUT)
c     strika      strike angle in degrees of the first nodal plane
c                  (OUTPUT)
c     dipa        dip angle in degrees of the first nodal plane
c                  (OUTPUT)
c     rakea       rake angle in degrees of the first nodal plane
c                  (OUTPUT)
c     slipa       dip direction in degrees of the first nodal plane
c                  (OUTPUT)
c     strikb      strike angle in degrees of the second nodal plane
c                  (OUTPUT)
c     dipb        dip angle in degrees of the second nodal plane
c                  (OUTPUT)
c     rakeb       rake angle in degrees of the second nodal plane
c                  (OUTPUT)
c     slipb       dip direction in degrees of the second nodal plane
c                  (OUTPUT)
c     trendp      trend angle in degrees of the P axis (OUTPUT)
c     plungp      plunge angle in degrees of the P axis (OUTPUT)
c     trendt      trend angle in degrees of the T axis (OUTPUT)
c     plungt      plunge angle in degrees of the T axis (OUTPUT)
c     trendb      trend angle in degrees of the B axis (OUTPUT)
c     plungb      plunge angle in degrees of the B axis (OUTPUT)
c     eta         percentage of CLVD remainder (OUTPUT)
c     ierr        error indicator (OUTPUT)

```

```

c
c      errors:
c      1           input tensor not symmetrical: am(1,2).ne.am(2,1)
c      2           input tensor not symmetrical: am(1,3).ne.am(3,1)
c      3           input tensor not symmetrical: am(2,3).ne.am(3,2)
c      5,6,7,8,9,10   internal errors
c
c      implicit none
c-----
-----
      integer io
      real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
-----
      real am,ama,am0,am1,e,am0b,strika,dipa,rakea,slipa,strikb,dipb
1,rakeb,slipb,trendp,plungp,trendt,plungt,trendb,plungb,eta
      integer ierr
      dimension am(3,3),ama(3,3)
c
      call fpsset
c
      am0=c0
      am1=c0
      e=c0
      am0b=c0
      strika=c0
      dipa=c0
      rakea=c0
      slipa=c0
      strikb=c0
      dipb=c0
      rakeb=c0
      slipb=c0
      trendp=c0
      plungp=c0
      trendt=c0
      plungt=c0
      trendb=c0
      plungb=c0
      ierr=0
      call ar2ha(am,ama,ierr)
      if(ierr.ne.0) then
          write(io,'(1x,a,i3)') 'HA2PLP: ierr=',ierr
          return
      endif
      call ar2plp(ama,am0,am1,e,am0b,strika,dipa,rakea,slipa,
1strikb,dipb,rakeb,slipb,trendp,plungp,trendt,plungt,trendb,
2plungb,eta,ierr)
      if(ierr.ne.0) then
          write(io,'(1x,a,i3)') 'HA2PLP: ierr=',ierr
      endif
      return
  end
*****
***** subroutine pl2ar(strike,dip,rake,am0,am,ierr)

```

```

c
c      compute moment tensor Cartesian components (Aki & Richards
convention)
c      from strike, dip and rake
c
c      usage:
c      call pl2ar(strike,dip,rake,am0,am,ierr)
c
c      arguments:
c      strike      strike angle in degrees (INPUT)
c      dip         dip angle in degrees (INPUT)
c      rake        rake angle in degrees (INPUT)
c      am0         scalar seismic moment (INPUT)
c      am          seismic moment tensor (3x3 matrix) (OUTPUT)
c      ierr        error indicator (OUTPUT)
c
c      errors:
c      1           input STRIKE angle out of range
c      2           input DIP angle out of range
c      4           input RAKE angle out of range
c      3           1+2
c      5           1+4
c      7           1+2+4
c      8           internal error
c
c      implicit none
c-----
-----  

      integer io
      real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----  

-----  

      real am,anx,any,anz,dx,dy,dz,am0,strike,dip,rake
      integer ierr,i,j
      dimension am(3,3)
c
      call fpsset
c
      do 1 i=1,3
         do 2 j=1,3
            am(i,j)=c0
2       continue
1       continue
      ierr=0
      call pl2nd(strike,dip,rake,anx,any,anz,dx,dy,dz,ierr)
      if(ierr.ne.0) then
         write(io,'(1x,a,i3)') 'PL2AR: ierr=',ierr
         return
      endif
      call nd2ar(anx,any,anz,dx,dy,dz,am0,am,ierr)
      if(ierr.ne.0) then
         ierr=8
         write(io,'(1x,a,i3)') 'PL2AR: ierr=',ierr
      endif
      return
end

```

```

*****
***** subroutine pl2ha(strike,dip,rake,am0,am,ierr)
c
c compute moment tensor Cartesian components (Harvard CMT convention)
c from strike, dip and rake
c
c usage:
c call pl2ha(strike,dip,rake,am0,am,ierr)
c
c arguments:
c strike      strike angle in degrees (INPUT)
c dip         dip angle in degrees (INPUT)
c rake        rake angle in degrees (INPUT)
c am0         scalar seismic moment (INPUT)
c am          seismic moment tensor (3x3 matrix) (OUTPUT)
c ierr        error indicator (OUTPUT)
c
c errors:
c 1           input STRIKE angle out of range
c 2           input DIP angle out of range
c 4           input RAKE angle out of range
c 3           1+2
c 5           1+4
c 7           1+2+4
c 8,9         internal errors
c
c implicit none
c-----
----- integer io
real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
----- real strike,dip,rake,am0,am
integer ierr,i,j
dimension am(3,3)
c
call fpsset
c
do 1 i=1,3
   do 2 j=1,3
      am(i,j)=c0
2      continue
1      continue
ierr=0
call pl2ar(strike,dip,rake,am0,am,ierr)
if(ierr.ne.0) then
   write(io,'(1x,a,i3)') 'PL2HA: ierr=',ierr
   return
endif
call ar2ha(am,am,ierr)
if(ierr.ne.0) then
   ierr=9
   write(io,'(1x,a,i3)') 'PL2HA: ierr=',ierr
endif

```

```

        return
    end
*****
***** subroutine pt2ar(trendp,plungp,trendt,plungt,am0,am,ierr)
c
c      compute moment tensor Cartesian components (Aki & Richards
convention)
c      from P and T axes
c
c      usage:
c      call pt2ar(trendp,plungp,trendt,plungt,am0,am)
c
c      arguments:
c      trendp          trend angle of P axis in degrees (INPUT)
c      plungp          plunge angle of P axis in degrees (INPUT)
c      trendt          trend angle of T axis in degrees (INPUT)
c      plungt          plunge angle of T axis in degrees (INPUT)
c      am0             scalar seismic moment (INPUT)
c      am              seismic moment tensor (3x3 matrix) (OUTPUT)
c      ierr            error indicator (OUTPUT)
c
c      errors:
c      1               input TREND angle of P axis out of range
c      2               input PLUNGE angle P axis out of range
c      3               1+2
c      4               input TREND angle of P axis out of range
c      5               input PLUNGE angle P axis out of range
c      6               4+5
c      8,9            internal errors
c
c      implicit none
c-----
----- integer io
real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
----- real trendp,plungp,trendt,plungt,am0,am,px,py,pz,tx,ty,tz
1,anx,any,anz,dx,dy,dz
integer ierr,i,j
dimension am(3,3)
c
call fpsset
c
do 1 i=1,3
    do 2 j=1,3
        am(i,j)=c0
2     continue
1     continue
ierr=0
call ax2ca(trendp,plungp,px,py,pz,ierr)
if(ierr.ne.0) then
    write(io,'(1x,a,i3)') 'PT2AR: ierr=',ierr
    return
endif

```

```

call ax2ca(trendt,plungt,tx,ty,tz,ierr)
if(ierr.ne.0) then
  ierr=ierr+3
  write(io,'(1x,a,i3)') 'PT2AR: ierr=',ierr
  return
endif
call pt2nd(px,py,pz,tx,ty,tz,anx,any,anz,dx,dy,dz,ierr)
if(ierr.ne.0) then
  ierr=8
  write(io,'(1x,a,i3)') 'PT2AR: ierr=',ierr
  return
endif
call nd2ar(anx,any,anz,dx,dy,dz,am0,am,ierr)
if(ierr.ne.0) then
  ierr=9
  write(io,'(1x,a,i3)') 'PT2AR: ierr=',ierr
endif
return
end
*****
***** subroutine pt2ha(trendp,plungp,trendt,plungt,am0,am,ierr)
c
c   compute moment tensor Cartesian components (Harvard CMT convention)
c   from P and T axes
c
c   usage:
c   call pt2ha(trendp,plungp,trendt,plungt,am0,am)
c
c   arguments:
c   trendp      trend angle of P axis in degrees (INPUT)
c   plungp      plunge angle of P axis in degrees (INPUT)
c   trendt      trend angle of T axis in degrees (INPUT)
c   plungt      plunge angle of T axis in degrees (INPUT)
c   am0         scalar seismic moment (INPUT)
c   am          seismic moment tensor (3x3 matrix) (OUTPUT)
c   ierr        error indicator (OUTPUT)
c
c   errors:
c   1           input TREND angle of P axis out of range
c   2           input PLUNGE angle P axis out of range
c   3           1+2
c   4           input TREND angle of P axis out of range
c   5           input PLUNGE angle P axis out of range
c   6           4+5
c   8,9,10      internal errors
c
c   implicit none
c-----
-----
      integer io
      real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
-----
      real trendp,plungp,trendt,plungt,am0,am
      integer ierr,i,j

```

```

dimension am(3,3)
c
call fpsset
c
do 1 i=1,3
   do 2 j=1,3
      am(i,j)=c0
2      continue
1 continue
ierr=0
call pt2ar(trendp,plungp,trendt,plungt,am0,am,ierr)
if(ierr.ne.0) then
   write(io,'(1x,a,i3)') 'PT2HA: ierr=',ierr
   return
endif
call ar2ha(am,am,ierr)
if(ierr.ne.0) then
   ierr=10
   write(io,'(1x,a,i3)') 'PT2HA: ierr=',ierr
endif
return
end
*****
***** UTILITY ROUTINES *****
*****
subroutine avec(am,eval,evec)
c
c      compute eigenvalues and eigenvectors
c
c      usage:
c      utility routine for internal use only
c
c      implicit none
c-----
-----
integer io
real amistr,amastr,midip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
common /fpscom/amistr,amastr,midip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
-----
real am,eval,evec,dum
integer i,j,k
dimension am(3,3),eval(3),evec(3,3)
c
call fpsset
c
CALL EVCSF (3, AM, 3, EVAL, EVEC, 3)
1 do 2 i=1,2
   do 3 j=i+1,3
      if(abs(eval(i)).lt.abs(eval(j))) then
         dum=eval(i)
         eval(i)=eval(j)
         eval(j)=dum
         do 4 k=1,3
            dum=evec(k,i)

```

```

        evec(k,i)=evec(k,j)
        evec(k,j)=dum
4         continue
        endif
3         continue
2         continue
        return
    end
*****
***** subroutine angle(wax,way,waz,wbx,wby,wbz,ang)
C
C      compute the angle (in degrees) between two vectors
C
C      usage:
C      call angle(wax,way,waz,wbx,wby,wbz,ang)
C
C      arguments:
C      wax,way,waz      Cartesian component of first vector (INPUT)
C      wbx,wby,wbz      Cartesian component of second vector (INPUT)
C      ang              angle between the two vectors in degrees (OUTPUT)
C
C      implicit none
C-----
-----
        integer io
        real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
        common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
C-----
-----
        real wax,way,waz,wbx,wby,wbz,ax,ay,az,bx,by,bz,ang
1,anorm,bnorm,prod
C
        call fpsset
C
        call norm(wax,way,waz,anorm,ax,ay,az)
        call norm(wbx,wby,wbz,bnorm,bx,by,bz)
        prod=ax*bx+ay*by+az*bz
        ang=acos(max(-c1,min(c1,prod))/dtor)
        return
    end
*****
***** subroutine angles(strika,dipa,rakea,strikb,dipb,rakeb,
1anglep,angled,ierr)
C
C      compute the angle (in degrees) between nodal planes and slip
vectors
C
C      usage:
C      call
angles(strikea,dipa,rakea,strikeb,dipb,rakeb,anglep,angled,ierr)
C
C      arguments:
C      strika          strike angle in degrees of the first nodal plane
(INPUT)

```

```

c      dipa           dip angle in degrees of the first nodal plane
c      (INPUT)
c      rakea          rake angle in degrees of the first nodal plane
c      (INPUT)
c      strikb         strike angle in degrees of the second nodal plane
c      (INPUT)
c      dipb           dip angle in degrees of the second nodal plane
c      (INPUT)
c      rakeb          rake angle in degrees of the second nodal plane
c      (INPUT)
c      anglep          angle in degrees between planes
c      angled          angle in degrees between slip directions
c      ierr            error indicator (OUTPUT)
c
c      errors:
c      1                input STRIKE angle of first plane out of range
c      2                input DIP angle of first plane out of range
c      4                input RAKE angle of first plane out of range
c      3                1+2
c      5                1+4
c      7                1+2+4
c      8                input STRIKE angle of first plane out of range
c      9                input DIP angle of first plane out of range
c      11               input RAKE angle of first plane out of range
c      10               8+9
c      13               8+11
c      15               8+9+11
c
c      implicit none
c-----
-----  

      integer io
      real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
      1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
      1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
      2,c3,io
c-----  

-----  

      real strika,dipa,rakea,strikb,dipb,rakeb,anglep,angled
      1,anax,anay,anaz,anbx,anby,anbz,dax,day,daz,dbx,dby,dbz
      integer ierr
c
      call fpsset
c
      call pl2nd(strika,dipa,rakea,anax,anay,anaz,dax,day,daz,ierr)
      if(ierr.ne.0) then
          write(io,'(1x,a,i3)') 'ANGLES: ierr=',ierr
          return
      endif
      call pl2nd(strikb,dipb,rakeb,anbx,anby,anbz,dbx,dby,dbz,ierr)
      if(ierr.ne.0) then
          ierr=ierr+8
          write(io,'(1x,a,i3)') 'ANGLES: ierr=',ierr
          return
      endif
      call angle(anax,anay,anaz,anbx,anby,anbz,anglep)
      call angle(dax,day,daz,dbx,dby,dbz,angled)
      return
  end

```

```

*****
***** subroutine anglea(trenda,plunga,trendb,plungb,ang,ierr)
c
c      usage:
c      call anglea(trenda,plunga,trendb,plungb,ang,ierr)
c
c      arguments:
c      trenda      clockwise angle from North in degrees of first axis
c      (INPUT)
c      plunga      inclination angle in degrees of first axis (INPUT)
c      trendb      clockwise angle from North in degrees of second axis
c      (INPUT)
c      plungb      inclination angle in degrees of second axis (INPUT)
c      ang         angle in degrees between the axes (OUTPUT)
c      ierr        error indicator (OUTPUT)
c
c      errors:
c      1           input TREND angle of first axis out of range
c      2           input PLUNGE angle of first axis out of range
c      3           1+2
c      5           input TREND angle of first axis out of range
c      6           input PLUNGE angle of first axis out of range
c      7           5+6
c
c      implicit none
c-----
-----
      integer io
      real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
      1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
      1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
      2,c3,io
c-----
-----
      real trenda,plunga,ax,ay,az,trendb,plungb,bx,by,bz,ang
      integer ierr
c
      call fpsset
c
      call ax2ca(trenda,plunga,ax,ay,az,ierr)
      if(ierr.ne.0) then
          write(io,'(1x,a,i3)') 'ANGLEA: ierr=',ierr
          return
      endif
      call ax2ca(trendb,plungb,bx,by,bz,ierr)
      if(ierr.ne.0) then
          ierr=ierr+4
          write(io,'(1x,a,i3)') 'ANGLEA: ierr=',ierr
          return
      endif
      call angle(ax,ay,az,bx,by,bz,ang)
      return
  end
*****
***** subroutine norm(wax,way,waz,anorm,ax,ay,az)
c
c      compute euclidean norm and verson components

```

```

c
c      usage:
c      call norm(wax,way,waz,anorm,ax,ay,az)
c
c      arguments:
c      wax,way,waz      Cartesian component of input vector (INPUT)
c      anorm            Euclidean norm of input vector (OUTPUT)
c      ax,ay,az         normalized Cartesian component of the vector
c                  (OUTPUT)
c
c      implicit none
c-----
-----
      integer io
      real amistr,amastr,midip,amadip,amirak,amarak,amitre,amatre
      1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,midip,amadip,amirak,amarak,amitre
      1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
      2,c3,io
c-----
-----
      real wax,way,waz,anorm,ax,ay,az
c
c      call fpsset
c
c      anorm=sqrt(wax*wax+way*way+waz*waz)
c      if(anorm.eq.c0) return
c      ax=wax/anorm
c      ay=way/anorm
c      az=waz/anorm
c      return
c      end
*****
***** subroutine vecpro(px,py,pz,tx,ty,tz,bx,by,bz)
c
c      compute vector products of two vectors
c
c      usage:
c      call vecpro(px,py,pz,tx,ty,tz,bx,by,bz)
c
c      arguments:
c
c      px,py,pz      Cartesian component of first vector (INPUT)
c      tx,ty,tz      Cartesian component of second vector (INPUT)
c      bx,by,bz      Cartesian component of vector product (OUTUT)
c
c      implicit none
c-----
-----
      integer io
      real amistr,amastr,midip,amadip,amirak,amarak,amitre,amatre
      1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,midip,amadip,amirak,amarak,amitre
      1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
      2,c3,io
c-----
-----
      real px,py,pz,tx,ty,tz,bx,by,bz
c

```

```

call fpsset
c
bx=py*tz-pz*ty
by=pz*tx-px*tz
bz=px*ty-py*tx
return
end
*****
***** subroutine invert(ax,ay,az)
c
c      invert vector
c
c      usage:
c      utility routine for internal use only
c
c      implicit none
c-----
-----
integer io
real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
common /fpscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
-----
real ax,ay,az
c
call fpsset
c
ax=-ax
ay=-ay
az=-az
return
end
*****
***** subroutine hatens(amrr,amss,amee,amrs,amre,amse,am)
c
c      build the Harvard CMT tensor from independent components
c
c      usage:
c      call hatens(amrr,amss,amee,amrs,amre,amse,am)
c
c      arguments:
c      amss          Harvard CMT South-South component (INPUT)
c      amse          Harvard CMT South-East component (INPUT)
c      amrs          Harvard CMT Radial-South component (INPUT)
c      amee          Harvard CMT East-East component (INPUT)
c      amre          Harvard CMT Radial-East component (INPUT)
c      amrr          Harvard CMT Radial-Radial component (INPUT)
c      am            seismic moment tensor (3x3 matrix) (OUTPUT)
c
c      implicit none
c-----
-----
integer io
real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3

```

```

common /fpscom/amistr,amastr,midip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
-----
      real am,amss,amse,amrs,amee,amre,amrr
      dimension am(3,3)
c
      call fpsset
c
      am(1,1)=amss
      am(1,2)=amse
      am(1,3)=amrs
      am(2,1)=amse
      am(2,2)=amee
      am(2,3)=amre
      am(3,1)=amrs
      am(3,2)=amre
      am(3,3)=amrr
      return
      end
*****
***** subroutine tensha(am,amrr,amss,amee,amrs,amre,amse)
c
c      give independent components from Harvard CMT tensor
c
c      usage:
c      call tensha(am,amrr,amss,amee,amrs,amre,amse)
c
c      arguments:
c      am          seismic moment tensor (3x3 matrix) (INPUT)
c      amss        Harvard CMT South-South component (OUTPUT)
c      amse        Harvard CMT South-East component (OUTPUT)
c      amrs        Harvard CMT Radial-South component (OUTPUT)
c      amee        Harvard CMT East-East component (OUTPUT)
c      amre        Harvard CMT Radial-East component (OUTPUT)
c      amrr        Harvard CMT Radial-Radial component (OUTPUT)
c
c      implicit none
c-----
-----
      integer io
      real amistr,amastr,midip,amadip,amirak,amarak,amitre,amatre,
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
      common /fpscom/amistr,amastr,midip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
-----
      real am,amss,amse,amrs,amee,amre,amrr
      dimension am(3,3)
c
      call fpsset
c
      amrr=am(3,3)
      amss=am(1,1)
      amee=am(2,2)
      amrs=am(3,1)
      amre=am(3,2)

```

```

amse=am(1,2)
return
end
*****
***** subroutine fpsset
c
c      define constants (i.e. input ranges and tolerances) used throughout
the
c      package. It is called by every subroutines to setup constants
c
c      usage:
c      call fpsset
c
c      constants in fpsscom common block:
c
c      amistr      strike lower limit
c      amastr      strike upper limit
c      amidip      dip lower limit
c      amadip      dip upper limit
c      amirak      rake lower limit
c      amarak      rake upper limit
c      amitre      trend lower limit
c      amatre      trend upper limit
c      amiplu     plunge lower limit
c      amaplu     plunge upper limit
c      orttol      orthogonality tolerance
c      ovrtol      dip overtaking tolerance
c      tentol      moment tensor symmetry tolerance
c      dtor       degree to radians
c      c360       360.
c      c90        90.
c      c0         0.
c      c1         1.
c      c2         2.
c      c3         3.
c      io          error messages file unit
c
c      implicit none
c-----
----- integer io
real amistr,amastr,amidip,amadip,amirak,amarak,amitre,amatre
1,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2,c3
common /fpsscom/amistr,amastr,amidip,amadip,amirak,amarak,amitre
1,amatre,amiplu,amaplu,orttol,ovrtol,tentol,dtor,c360,c90,c0,c1,c2
2,c3,io
c-----
----- integer ifl
save ifl
data ifl/0/
if(ifl.eq.0) then
    amistr=-360.
    amastr=360.
    amidip=0.
    amadip=90.
    amirak=-360.
    amarak=360.
    amitre=-360.

```

```
amatre=360.  
amiplu=0.  
amaplu=90.  
orttol=2.  
ovrtol=0.001  
tentol=0.0001  
dtor=0.017453292519943296  
c360=360.  
c90=90.  
c0=0.  
c1=1.  
c2=2.  
c3=3.  
io=6  
ifl=1  
endif  
return  
end
```